

# Physics 2326 - Formula List

## Integrals

$$\int u^n du = \frac{u^{n+1}}{n+1} + C \quad (n \neq -1) \quad \int \frac{du}{\sqrt{a^2 - u^2}} = \arcsin\left(\frac{u}{a}\right) + C$$

$$\int \frac{du}{u} = \ln|u| + C \quad \int \frac{du}{\sqrt{u^2 + a^2}} = \ln\left(u + \sqrt{u^2 + a^2}\right) + C$$

$$\int e^{au} du = \frac{1}{a} e^{au} + C \quad \int \frac{du}{u^2 + a^2} = \frac{1}{a} \arctan\left(\frac{u}{a}\right) + C$$

$$\int \sin(au) du = -\frac{1}{a} \cos(au) + C \quad \int \frac{du}{(u^2 + a^2)^{3/2}} = \frac{1}{a^2} \frac{u}{\sqrt{u^2 + a^2}} + C$$

$$\int \cos(au) du = \frac{1}{a} \sin(au) + C \quad \int \frac{u du}{(u^2 + a^2)^{3/2}} = -\frac{1}{\sqrt{u^2 + a^2}} + C$$

■ **Coulomb's Law**  $F = k_e \frac{|Q_1||Q_2|}{r^2}$  (magnitude of force)

$$\vec{F}_{21} = k_e Q_1 Q_2 \frac{\hat{r}_{12}}{r_{12}^2} \text{ where } \hat{r}_{12} = \frac{\vec{r}_{12}}{r_{12}}$$

and where  $\vec{r}_{12}$  is the vector from  $Q_1$  to  $Q_2$ .  
Charge quantization:  $Q = ne$ ,  $n$  is an integer.

■ **Electric Field**  $\vec{E} = \vec{F}/q_0$  or  $\vec{E} = \lim_{q_0 \rightarrow 0} \vec{F}/q_0$ ,  $\vec{F} = Q\vec{E}$  (force on  $Q$ )

Point Charge:  $\vec{E} = k_e Q \frac{\hat{r}}{r^2} = k_e Q \frac{\vec{r}}{r^3}$ ,  $E = k_e \frac{|Q|}{r^2}$

Discrete:  $\vec{E} = k_e \sum_i Q_i \frac{\hat{r}_i}{r_i^2} = k_e \sum_i Q_i \frac{\vec{r}_i}{r_i^3}$

Continuous:  $\vec{E} = k_e \int \frac{\hat{r}}{r^2} dq = k_e \int \frac{\vec{r}}{r^3} dq$

$$\vec{E} = k_e Q \frac{\hat{z}}{(R^2 + z^2)^{3/2}} \quad (\hat{z} \text{ from center of uniform ring})$$

■ **Electric Flux**  $\Phi = \int \vec{E} \cdot d\vec{A}$ , uniform  $\vec{E}$  and flat surface:  $\Phi = \vec{E} \cdot \vec{A}$

Dot Product:  $\vec{A} \cdot \vec{B} = AB \cos \theta = A_x B_x + A_y B_y + A_z B_z$

■ **Gauss's Law**  $\oint \vec{E} \cdot d\vec{A} = \frac{1}{\epsilon_0} Q_{\text{enclosed}}$

■ **Potential and Potential Energy**  $V = U/q_0$ ,  $\Delta U = Q\Delta V$

For a charge distribution:  $U = k_e \sum_{i < j} \frac{Q_i Q_j}{r_{ij}}$

Conservation of Energy:  $K_i + U_i = K_f + U_f$ , where  $K = \frac{1}{2} m v^2$

■ **Potential due to Charges** Point Charge:  $V = k_e \frac{Q}{r}$

Discrete:  $V = k_e \sum_i \frac{Q_i}{r_i}$ , Continuous:  $V = k_e \int \frac{dq}{r}$

■ **Potential and Electric Field**  $\Delta V = -\int \vec{E} \cdot d\vec{r}$ ,  $\Delta V = -\vec{E} \cdot \Delta \vec{r}$  (uniform  $\vec{E}$ )

$E_x = -\frac{\partial V}{\partial x}$  and for  $y$  and  $z$ , also  $E_r = -\frac{\partial V}{\partial r}$

■ **Conductors in Electrostatics** At surface:  $\vec{E} \perp$  surface and  $E = \sigma/\epsilon_0$

Inside:  $\vec{E} = \vec{0}$ , voltage is const., no excess charge.

■ **Capacitance**  $Q = CV$ ,  $C$  is the capacitance.

$C = \kappa C_0$ , where  $C_0 =$  empty cap. and dielectric const.  $= \kappa \geq 1$

$C_0 = \frac{\epsilon_0 A}{d}$  (|| plate),  $C_0 = \frac{1}{k_e \left(\frac{1}{a} - \frac{1}{b}\right)}$  (sph.),  $C_0 = \frac{2\pi \epsilon_0 \ell}{\ln(b/a)}$  (cyl.)

■ **Energy**  $U = \frac{1}{2} C V^2 = \frac{Q^2}{2C} = \frac{1}{2} QV$  (energy in a cap.)

$u = \frac{\epsilon_0}{2} E^2 = \frac{\text{Energy}}{\text{Volume}}$  (energy density in a field)

■ **Electric Dipoles** Dipole Moment:  $\vec{p} = Q\vec{d}$ ,  $\vec{d}$  from  $-Q$  to  $Q$

Torque:  $\vec{\tau} = \vec{p} \times \vec{E}$ ,  $\tau = pE \sin \theta$ , Pot. Energy:  $U = -\vec{p} \cdot \vec{E}$

■ **Current and Current Density**  $I = \frac{dQ}{dt}$  (current through surface)

$\vec{J}$  is the current density.  $I = \int_{\text{surface}} \vec{J} \cdot d\vec{A}$ ,  $I = JA$  (for a wire)

■ **Drift Velocity**  $I = n|q|v_d A$ ,  $\vec{J} = nq\vec{v}_d$

$n = \frac{\# \text{ of charge carriers}}{\text{vol.}}$ ,  $q =$  charge of charge carriers,  $\vec{v}_d =$  drift vel.

■ **Ohm's Law**  $V = IR$ ,  $R = \frac{\rho L}{A}$ ,  $\vec{J} = \sigma \vec{E}$

$\sigma =$  conductivity,  $\rho = \frac{1}{\sigma} =$  resistivity

■ **Temperature Dependence**  $\Delta T = T - T_0$

$\Delta R = \alpha R_0 \Delta T$ ,  $R = R_0(1 + \alpha \Delta T)$ ,  $\Delta \rho = \alpha \rho_0 \Delta T$ ,  $\rho = \rho_0(1 + \alpha \Delta T)$

■ **Power**  $\mathcal{P} = VI$ , For a resistor:  $\mathcal{P} = VI = I^2 R = \frac{V^2}{R}$

## Combinations of Resistors

Series:  $R_{\text{eq}} = R_1 + R_2 + \dots$ , Parallel:  $R_{\text{eq}} = \left(\frac{1}{R_1} + \frac{1}{R_2} + \dots\right)^{-1}$

Node Reduction:  $R'_{ij} = \frac{R_i R_j}{R_{ij}}$ , where  $R_{ij} = \left(\frac{1}{R_1} + \frac{1}{R_2} + \frac{1}{R_3}\right)^{-1}$

## Combinations of Capacitors

Series:  $C_{\text{eq}} = \left(\frac{1}{C_1} + \frac{1}{C_2} + \dots\right)^{-1}$ , Parallel:  $C_{\text{eq}} = C_1 + C_2 + \dots$

■ **Kirchhoff's Rules** Junctions:  $\sum I_{\text{in}} = \sum I_{\text{out}}$ , Loops:  $0 = \sum \Delta V$

■ **Cross or Vector Product**  $\vec{A} \times \vec{B} = \hat{u} AB \sin \theta$ , right hand rule  $\Rightarrow \hat{u}$

$$\vec{A} \times \vec{B} = \begin{vmatrix} \hat{x} & \hat{y} & \hat{z} \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{vmatrix} = \hat{x} \begin{vmatrix} A_y & A_z \\ B_y & B_z \end{vmatrix} - \hat{y} \begin{vmatrix} A_x & A_z \\ B_x & B_z \end{vmatrix} + \hat{z} \begin{vmatrix} A_x & A_y \\ B_x & B_y \end{vmatrix}$$

■ **Magnetic Force on Particle**  $\vec{F} = Q\vec{v} \times \vec{B}$

$\vec{v} \perp$  to uniform  $\vec{B} \Rightarrow$  circle with  $r = \frac{mv}{|Q|B}$

■ **Magnetic Force on Wire**  $\vec{F} = I \int d\vec{r} \times \vec{B}$

$\vec{F} = I \vec{\ell} \times \vec{B}$  (straight segment, uniform field)

$V_{\text{Hall}} = v_d B L$  (Hall Voltage)

■ **Magnetic Dipoles** Dipole Moment:  $\vec{\mu} = NI\vec{A}$  ( $N$  is # of turns)

Torque:  $\vec{\tau} = \vec{\mu} \times \vec{B}$ ,  $\tau = \mu B \sin \theta$ , Pot. Energy:  $U = -\vec{\mu} \cdot \vec{B}$

■ **Biot-Savart Law**  $\vec{B} = \frac{\mu_0 I}{4\pi} \int d\vec{s} \times \frac{\hat{r}}{r^2}$

$\vec{B} = \hat{z} \frac{\mu_0 I}{4\pi R} \theta$  (at center of arc in  $xy$ -plane)

$\vec{B} = \hat{z} \frac{\mu_0 I}{2} \frac{R^2}{(R^2 + z^2)^{3/2}}$  ( $z$  from center of circle)

$$B = \frac{\mu_0 I}{4\pi a} (\sin \phi_2 - \sin \phi_1) = \frac{\mu_0 I}{4\pi a} \left( \frac{x_2}{\sqrt{x_2^2 + a^2}} - \frac{x_1}{\sqrt{x_1^2 + a^2}} \right) \text{ (segment)}$$

$B = \frac{\mu_0 I}{2\pi r}$  (distance  $r$  from long wire)

■ **Ampere's Law**  $\oint \vec{B} \cdot d\vec{r} = \mu_0 I_{\text{enclosed}}$

$B = \mu_0 n I$ ,  $n = \frac{\# \text{ of turns}}{\text{length}}$  (inside long solenoid)

■ **Magnetic Flux**  $\Phi_m = \int \vec{B} \cdot d\vec{A}$

For uniform field and flat surface:  $\Phi = \vec{B} \cdot \vec{A}$

■ **Faraday's Law**  $\mathcal{E} = -N \frac{d\Phi}{dt}$ ,  $\vec{\mathcal{E}} = -N \frac{\Delta\Phi}{\Delta t}$   
 AC Generator:  $\Phi = BA \cos \omega t \implies \mathcal{E}(t) = NBA \omega \sin \omega t$

■ **Motional EMF**

moving rod:  $\mathcal{E} = B \ell v$  ( $\vec{B} \perp \vec{v} \perp \text{rod}$ )  
 rotating rod:  $\mathcal{E} = \frac{1}{2} B \ell^2 \omega$  ( $\vec{B} \parallel \text{axis} \perp \text{rod}$ )

■ **Lenz's Law**

Direction for  $\Phi$  is dir. of field through loop.  
 $\frac{d\Phi}{dt}$  is same as (opposite to) dir. for  $\Phi$  when increasing (decreasing).  
 $\Phi_{\text{induced}}$  dir. is opposite to dir. for  $\frac{d\Phi}{dt}$ .  
 Get direction of  $\mathcal{E}$  or  $I$  by Right Hand Rule.

■ **Maxwell's Equations**

$\oint \vec{E} \cdot d\vec{A} = \frac{1}{\epsilon_0} Q_{\text{enc}}$ ,  $\oint \vec{B} \cdot d\vec{A} = 0$   
 $\oint \vec{B} \cdot d\vec{r} = \mu_0 I_{\text{enc}} + \mu_0 \epsilon_0 \frac{d\Phi_e}{dt}$ ,  $\oint \vec{E} \cdot d\vec{r} = -\frac{d\Phi_m}{dt}$

■ **Inductance** Mutual:  $\mathcal{E}_2 = -M \frac{dI_1}{dt}$ , Self:  $\mathcal{E} = -L \frac{dI}{dt}$

Long Solenoid:  $L = \mu_0 n^2 A \ell = \mu_0 \frac{N^2}{\ell} A$

Energy in Inductor:  $U = \frac{1}{2} L I^2$

■ **Energy Density**  $u = \frac{1}{2\mu_0} B^2$  (in magnetic field)

$u = u_e + u_m = \frac{\epsilon_0}{2} E^2 + \frac{1}{2\mu_0} B^2$  (in electromagnetic field)

■ **RC Circuits**  $\tau = RC = \text{time const.}$ ,  $\mathcal{E} = \text{EMF}$

Discharging:  $Q(t) = Q_0 e^{-t/\tau}$  Charging:  $Q(t) = C\mathcal{E}(1 - e^{-t/\tau})$

■ **RL Circuits**  $\tau = \frac{L}{R} = \text{time const.}$

Current Growth:  $I(t) = \frac{\mathcal{E}}{R}(1 - e^{-t/\tau})$ , Current Decay:  $I(t) = I_0 e^{-t/\tau}$

■ **LC Circuits**  $\omega_0 = \frac{1}{\sqrt{LC}}$ ,  $Q(t) = Q_{\text{max}} \cos(\omega_0 t + \phi)$

■ **LCR Circuits**  $Q(t) = Q_0 e^{-\gamma t} \cos(\omega t + \phi)$ ,  $\gamma = \frac{R}{2L}$ ,  $\omega = \sqrt{\omega_0^2 - \gamma^2}$

■ **General AC Circuits**  $V_{\text{rms}} = \frac{1}{\sqrt{2}} V_{\text{max}}$ ,  $I_{\text{rms}} = \frac{1}{\sqrt{2}} I_{\text{max}}$

$\omega = 2\pi f$ ,  $I(t) = I_{\text{max}} \cos \omega t$ ,  $V(t) = V_{\text{max}} \cos(\omega t + \phi)$

$Z = \frac{V_{\text{max}}}{I_{\text{max}}} = \frac{V_{\text{rms}}}{I_{\text{rms}}}$  (Impedance),  $\bar{P} = V_{\text{rms}} I_{\text{rms}} \cos \phi$  (Average Power)

	Z	$\phi$
Just R	R	0
Just C	$X_C = \frac{1}{\omega C}$	$-90^\circ = -\frac{\pi}{2}$
Just L	$X_L = \omega L$	$90^\circ = \frac{\pi}{2}$

■ **Series RCL**  $Z = \sqrt{R^2 + (X_L - X_C)^2}$ ,  $\tan \phi = \frac{X_L - X_C}{R}$ ,  $\bar{P} = I_{\text{rms}}^2 R$

Resonance:  $Z = Z_{\text{min}} = R \iff X_L = X_C \iff \omega = \frac{1}{\sqrt{LC}}$

■ **Transformer**  $\frac{V_2}{V_1} = \frac{N_2}{N_1} = \frac{I_1}{I_2}$

■ **Electromagnetic Radiation in Vacuum**

$\vec{E} = \hat{y} E_{\text{max}} \cos(kx - \omega t)$ ,  $\vec{B} = \hat{z} B_{\text{max}} \cos(kx - \omega t)$

$\omega = 2\pi f = \frac{2\pi}{T}$ ,  $k = \frac{2\pi}{\lambda}$ ,  $f\lambda = \frac{\omega}{k} = c = \frac{1}{\sqrt{\mu_0 \epsilon_0}}$ ,  $c = \frac{E_{\text{max}}}{B_{\text{max}}} = \frac{E}{B}$

Intensity =  $I = \frac{\text{Power}}{\text{Area}} = \frac{U}{A \Delta t}$ ,  $I = \frac{E_{\text{max}}^2}{2\mu_0 c} = c \bar{u} = \bar{S}$ ,  $\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$

■ **Radiation Pressure and Momentum**

Momentum carried by radiation:  $p = \frac{U}{c}$ , Pressure =  $\frac{\text{Force}}{\text{Area}}$

	Momentum to Surface	Pressure on Surface
Perfect Absorber	$p = \frac{U}{c}$	$P = \frac{I}{c}$
Perfect Reflector	$p = 2 \frac{U}{c}$	$P = 2 \frac{I}{c}$
$\kappa = \text{fraction refl.}$	$p = (1 + \kappa) \frac{U}{c}$	$P = (1 + \kappa) \frac{I}{c}$

■ **In a Medium**  $f\lambda = v = c/n$

At interface:  $n_1 \lambda_1 = n_2 \lambda_2$

Snell's Law:  $n_1 \sin \theta_1 = n_2 \sin \theta_2$

Total Internal Refl.:  $\theta_1 > \theta_c$  where  $\sin \theta_c = \frac{n_2}{n_1}$

■ **Geometric Optics**  $\frac{1}{f} = \frac{1}{s} + \frac{1}{s'}$ ,  $m = \frac{h'}{h} = -\frac{s'}{s}$

Sph. Mirrors:  $f = \frac{R}{2}$ ,  $R > 0$  (concave),  $R < 0$  (convex),  $R \rightarrow \infty$  (flat)

Thin Lenses:  $f > 0$  (converging),  $f < 0$  (diverging)

Spherical Interface:  $\frac{n_1}{s} + \frac{n_2}{s'} = \frac{n_2 - n_1}{R}$ ,  $m = \frac{h'}{h} = -\frac{n_1 s'}{n_2 s}$

Flat Interface:  $\frac{s'}{s} = -\frac{n_2}{n_1}$ ,  $m = \frac{h'}{h} = 1$

Lensmaker Formula:  $\frac{1}{f} = (n - 1) \left( \frac{1}{R_1} - \frac{1}{R_2} \right)$

■ **Interference and Diffraction**

$\tan \theta = \frac{y}{L}$ , Small  $\theta$  or  $y \ll L \implies \sin \theta = \frac{y}{L}$

**Double Slit:** Intensity:  $I = I_{\text{max}} \cos^2 \left( \frac{\pi d \sin \theta}{\lambda} \right)$

Const. Int.:  $d \sin \theta = m\lambda$ , Dest. Int.:  $d \sin \theta = \left(m + \frac{1}{2}\right)\lambda$

**Diffraction Grating:** Const. Int:  $d \sin \theta = m\lambda$ , Dest. Int. elsewhere

**Single Slit:** Destr. Int.:  $a \sin \theta = m\lambda$ ,  $m \neq 0$

Thin Films	Constructive Interference	Destructive Interference
$n < n'$	$2t = m \frac{\lambda}{n}$	$2t = \left(m + \frac{1}{2}\right) \frac{\lambda}{n}$
$n > n'$	$2t = \left(m + \frac{1}{2}\right) \frac{\lambda}{n}$	$2t = m \frac{\lambda}{n}$

**Phase Shift on Reflection:**  $n < n' \implies 180^\circ$  shift,  $n > n' \implies$  no shift

■ **Polarization**  $I = \frac{1}{2} I_0$ ,  $I = I_0 \cos^2 \theta$ ,  $\tan \theta_p = \frac{n_2}{n_1}$  (Pol.  $\perp$ )